Matching sensor overlap

Jose Eduardo Meireles


The problem

Instruments may measure different spectral ranges using different sensors, resulting in abrupt "jumps" in the reflectance or radiance data. In such cases, the regions between sensors need to be matched, i.e. spliced together.


Umatched spectra collected with a 3-sensor instrument, such as the SVC HR1024, may look like this:

```
# Path to raw (unmatched) spectra
path_raw = system.file("extdata/svc_raw_and_overlap_matched_serbin/SVC_Files/",
                       package = "spectrolab")
# Read spectra as reflectance and radiance
reflect_raw = read_spectra(path = path_raw,
                            format = "SIG",
                            type = "target_reflectance")
radiance_raw = read_spectra(path = path_raw,
                           format = "SIG",
                            type = "target_radiance")
# Sensor overlaps marked with vertical dashed lines
lwd = 0.5
cex = 0.7
par(mfrow = c(2, 1))
plot(reflect_raw, main = "Reflectance",
     lwd = lwd, cex.main = cex, cex.lab = cex, cex.axis = cex)
abline(v = c(990, 1900), col = "red", lty = 2, lwd = lwd)
plot(radiance_raw, main = "Radiance",
     lwd = lwd, cex.main = cex, cex.lab = cex, cex.axis = cex)
abline(v = c(990, 1900), col = "red", lty = 2, lwd = lwd)
```

Reflectance




Radiance




The solution

Use the function match_sensors to splice the sensor overlap regions as shown below. You must pass the boundary between sensors using the splice_at argument. It is critical that you get those bands right and every instrument (even from the same vendor) is different. You can use plot_interactive zoom into a particular spectral region and decide what the splice_at values should be.

Reflectance




Radiance



And we can check the results from spectrolab's match_sensors against SVC's proprietary matching algorithm.

Reflectance



Radiance

